DIPimage User Manual

dr. ir. Cris L. Luengo Hendriks prof. dr. ir. Lucas J. van Vliet dr. dipl. phys. Bernd Rieger dr. ir. Michael van Ginkel ing. Ronald Ligteringen

Contents

1	Int	roduction
	1.1	The DIP image toolbox
	1.2	The DIP lib library
	1.3	Image Processing
	1.4	Documentation Conventions
	1.5	Acknowledgements
2	Ins	talling DIPimage
	2.1	Windows Installation
	2.2	UNIX Installation
	2.3	MacOS X Installation
		2.3.1 Using MATLAB on MacOS X
		2.3.2 Slightly related tips
3	Get	tting Started
	3.1	Starting the GUI
	3.2	Loading and Displaying an Image
	3.3	Pre-processing the Image
	3.4	Measuring
	3.5	Where to Go from Here
Ļ	The	e dip_image Object
	4.1	Creating a dip_image Object
	4.2	Displaying dip_image Objects
	4.3	Operations on dip_image Objects
	4.4	Indexing Pixels
	4.5	Dimensions
	4.6	Image Arrays
	4.7	Tensor Images
	4.8	Color Images
	4.9	A Note on the end Method in Indexing
	4.10	Special Functions
	4.11	Review of the Differences Between a dip_image and a MATLAB Array
	The	e dip_measurement Object
	5.1	Extracting Measurement Data
	5.2	Other Information on the dip_measurement Object
	5.3	Combining Measurement Data
	5.4	Converting a dip_measurement Object to a dataset Object
	5.5	Creating a dip_measurement Object with Your Own Data

IV Contents

	5.6	Backwards Compatibility	26
6	Fig	rure Windows	27
	6.1	The Figure Window Menus	27
	6.2	Using the Mouse in Figure Windows	28
	6.3	Using the Keyboard in Figure Windows	29
	6.4	Linking Variables with Figure Windows	30
	6.5	Setting the Position of Figure Windows	30
7	Too	olbox Functions	32
	7.1	The GUI: dipimage	32
	7.2	The dipshow Function	32
	7.3	Figure Window Support: dipmapping	33
	7.4	Figure Window Support: diptruesize	33
	7.5	Figure Window Support: diptest, dipzoom, et al	34
	7.6	Figure Window Support: diplink	34
	7.7	Creating, Linking and Clearing Figure Windows: dipfig and dipclf	35
	7.8	Toolbox Preferences: dipsetpref and dipgetpref	35
	7.9	Interactive Tools: dipcrop, dipgetcoords, et al	36
	7.10	Image Processing Functions	36
		Adding Functions to the GUI	36
			41
	1.12	Automatic Parameter Parsing	41
8		8	42
	8.1	Figure Windows	42
	8.2	Graphical user Interface	42
	8.3	Initialization File	43
	8.4	Other Settings	43
9	Lov	w-level DIP lib Interface	49
	9.1	The Setup	49
	9.2	Calling DIP lib Functions	49
	9.3	Example Function Call	50

Introduction

1.1 The DIP image toolbox

MATLAB is a software package designed for (among other things) data processing. It contains a huge amount of numerical algorithms, and very good data-visualization abilities. This makes it adequate for image processing. However, MATLAB's virtues do not end there. It is also an ideal tool for rapid prototyping, since it handles a compact but simple notation and it is very easy to add functions to it. The drawback is that MATLAB, since it is an interpreted language, is slow for some constructs like loops; it also is not very efficient with memory (for example, all MATLAB data uses 8-byte floats). This makes it a bit less useful beyond the prototyping stage.

DIP*image* is a MATLAB toolbox for doing image processing, and is based on the image-processing library DIP*lib*. It is meant as a tool for research as well as teaching image processing at various levels. It is not meant as an industrial image-processing package, which should heavily depend on speed and memory-efficiency. Instead, this toolbox is made with user-friendliness, ease of implementation of new features, and compactness of notation in mind.

Most arithmetic operations are done by MATLAB. However, implementing image-processing filters usually requires several nested loops (depending on the dimensionality of the input data), which is not very efficient. Therefore, we based this toolbox on DIP lib. It provides all filtering and transform functions and is the heart of the DIP image toolbox.

1.2 The DIPlib library

DIP lib is a scientific image-processing library written in C. It contains a large number of functions for processing and analyzing multi-dimensional image data. The library provides functions for performing transforms, filter operations, object generation, and statistical analysis of images. It is also very efficient (with both memory and time).

The MATLAB interface to DIP *lib* is a simple "glue" layer, which allows calling the C functions in the library by converting the MATLAB data to a form used by the library. Only a few functions have added functionality in the interface. Using these functions therefore is much like using the C functions directly. This is not adequate for the beginning image analyst, who is better off using the DIP *image* toolbox functions instead.

More information on DIP *lib* can be found at: http://www.qi.tnw.tudelft.nl/DIP *lib*/.

1.3 Image Processing

This manual is meant as an introduction and reference to the DIP *image* toolbox, not as a tutorial on image processing. Although Chapter 3 shows some image-processing basics, it is not complete. We refer to "The Fundamentals of Image Processing", an online image-processing course, which can be found at:

http://www.qi.tnw.tudelft.nl/DIPlib/docs/FIP.pdf.

1.4 Documentation Conventions

The following conventions are used throughout this manual:

- Example code: in typewriter font
- File names and URLs: in typewriter font
- Function names/syntax: in typewriter font
- Keys: in **bold**
- Mathematical expressions: in *italic*
- Menu names, menu items, and controls: "inside quotes"
- Description of incomplete features: in *italic*

1.5 Acknowledgements

DIP *lib* was written mainly by Michael van Ginkel, Geert van Kempen, Cris Luengo and Lucas van Vliet; the MATLAB interface to DIP *lib* was written by Cris Luengo, with help from Michael van Ginkel.

The DIP*image* toolbox was written mainly by Cris Luengo, Lucas van Vliet, Bernd Rieger and Michael van Ginkel. Tuan Pham, Kees van Wijk, Judith Dijk, Geert van Kempen and Peter Bakker have contributed functionality.

DIP*lib* and the DIP*image* toolbox are being developed at the Quantitative Imaging Group, Delft University of Technology. Lucas van Vliet is the project supervisor.

Installing DIP image

This toolbox requires MATLAB 5.3 or later. Some functionality is only available on MATLAB 6 or on the Windows platform, but this is an exception. The bulk of the toolbox is platform-independent.

2.1 Windows Installation

If you have an earlier version of DIP *image* installed, it is important that you remove it before installing this version. Either delete or rename the whole directory. Make sure to remove or rename the files libdip.dll, libdipio.dll and libdml.dll, if they are present in the MATLAB\bin\ or the MATLAB\bin\ win32\ directory, or the system directory.

Note: depending on the version of DIP*image* you previously had, it is possible that you don't have the three files named above. Instead, you will have three files named DIPlib.dll, dipIO.dll and dipmex.dll. These files won't interfere with a new installation.

Unzip the distribution file dipimage.zip to a new directory (say, C:\newdir\). It will generate two sub-directories: C:\newdir\dipimage\ and C:\newdir\bin\. The first one contains the MATLAB toolbox, the second one the DIP lib library and two support libraries. The system (Windows, not MATLAB) must be able to find these library files. This can be accomplished one of the following ways:

- Add the C:\newdir\bin\ directory to the PATH environment variable. Environment variables can be set through the 'System' control panel. (If this doesn't mean anything to you, use one of the other methods.)
- Copy the three files (libdip.dll, libdipio.dll and libdml.dll) from the C:\newdir\bin\ directory to MATLAB's bin directory:
 - if you have MATLAB 5: C:\MATLABR11\bin\.
 - if you have MATLAB 6: C:\MATLABR12\bin\win32\.
- Copy these three files to the system directory (C:\WINNT\system32\). This option is better than the previous one if you are also going to use DIP lib independently from MATLAB.

You also might want to unzip the images file images.zip to the same directory. It will create a directory C:\newdir\images\ with some default images.

To start using DIP *image*, do the following in MATLAB:

(make sure to substitute 'C:\newdir\' for the name of the directory where you unzipped the distribution file). This will add the DIP image toolbox and low-level DIP lib interface to the beginning of the path, initialize DIP lib and set the default directory where DIP image will look for images.

You can add these lines to your startup.m file, which should be in your working directory. That way, DIP image will be ready to use each time you start MATLAB.

Optionally, you can add these directories to your path too:

```
[diproot,'\dipimage\demos']
[diproot,'\dipimage\aliases']
```

The first one contains a few demos that show how to use different features of the toolbox. The second one contains aliases for functions that have changed their names since the first release. You will need these aliases if you have written M-files that use any of the functions that have changed names (however, we recommend you change your functions to use the new names).

2.2 UNIX Installation

If you already have a version of DIP image installed, rename the directory it is in, so that you will still have the old version if the installation of the new version fails. Untar the distribution file. It will create a directory dip/ with a number of subdirectories. If you untarred the file in the directory /something/, you now have a directory /something/dip/. To get DIP image running, there are a number of things that you must do:

- 1. MATLAB must be told where it can find DIP*lib*, a shared library, that is used by DIP*image*. You can do this by creating the environment variable LD_LIBRARY_PATH, or extending it if it already exists. As the name suggests, it holds a collection of paths. The entries are separated by colons, i.e. ':'. Which entry you should add, depends on the type of machine you are working on:
 - On Solaris add: /something/dip/SunOS/lib/
 - On Linux add: /something/dip/Linux/lib/
- 2. If you did not do so before: download the separate tar or zip file containing some test images. Install them somewhere on your system. Let us assume that you installed them in /herebeimages/.

3. Add the following lines to your startup.m (preferably in \$HOME/matlab/):

This will add the DIP *image* toolbox and low-level DIP *lib* interface to the beginning of the path, initialize DIP *lib* and set the default directory where DIP *image* will look for images.

Optionally, you can add these directories to your path too:

```
[diproot,'/dipimage/demos']
[diproot,'/dipimage/aliases']
```

The first one contains a few demos that show how to use different features of the toolbox. The second one contains aliases for functions that have changed their names since the first release. You will need these aliases if you have written M-files that use any of the functions that have changed names (however, we recommend you change your functions to use the new names).

2.3 MacOS X Installation

For installation of DIP *image* on the MacOS X platform you must use the unix shell and follow the instructions as described in Section 2.2. The entry for this platform will be:

• On MacOS X add: /something/dip/Darwin/lib/

NOTE: as it turns out, in some occasions Darwin (the unix of MacOS X) does not look at LD_LIBRARY_PATH. As a result the DIP lib libraries cannot be found during the startup of MATLAB. As a workaround of this problem copy all files from /something/dip/Darwin/lib/to /usr/lib/!

2.3.1 Using MATLAB on MacOS X

The following is for the brave of heart. Follow these tips at your own risk!

When using the default installation of MATLAB for MacOS X the script will install Orobox-OSX as well. This window manager works together with XDarwin. As it turns out, the new X11 distribution from Apple is much faster then XDarwin and also comes included with its own window manager. You can change the startup script of MATLAB removing the startup of OroborOSX and add the startup of X11.

Note that as of Matlab R13 X11 is used and these steps are no longer needed!

Depending on were you installed MATLAB the startup script can be found somewhere here:

/Applications/MATLAB6p5/bin/LaunchMATLAB.app/Contents/launch_matlab.sh

\#!/bin/sh

Below is this modified script to use X11 (make sure to modify the paths to your settings):

```
if [ "'ps axc | grep X11'" ]; then
    sleeptime=30
else
    /Applications/X11.app/Contents/MacOS/X11 \&
    sleeptime=35
fi

cd ../..
bin/mac/setsid bin/matlab -desktop -display :0.0 \&
\# Bounce to let user know MATLAB is starting up.
/bin/sleep \$sleeptime
```

2.3.2 Slightly related tips...

During the process of porting DIP*lib* to MacOS X I found it extremely handy to use the 'Fink' project. This package manager allows you to conveniently select from a vast amount of precompiled binary packages and to install them. For more information check: http://fink.sourceforge.net/.

Installing of MacOS X on a non-G3/G4 machine can be **tried** with XPostFacto. Remember to start off with at least MacOS 9.1!. For more information check: http://eshop.macsales.com/OSXCenter/XPostFacto/.

Getting Started

To show you around DIP *image*, we will work through a simple image-processing application. Not all steps will be written out explicitly, since it is our goal to make you understand what is going on, and not to have you copy some commands and stare in amazement at the result.


The goal of this application is to do some measurements on an image of some rice grains, then analyze these measurements.

3.1 Starting the GUI

Type the following command at the MATLAB prompt:

dipimage


This should start the DIP*image* GUI. A new window appears to the top-left of the screen, which contains a menu bar. Spend some time exploring the menus. When you choose one of the options, the area beneath the menu bar should change into a dialog box that allows you to enter the parameters for the filter you have chosen. See also Sections 7.1 and 8.2 for more info on the GUI.



3.2 Loading and Displaying an Image

Before you can use these functions, you first need to load some image. The first menu is called "File I/O", and its first item "Read image (readim)". Select it. Press the "Browse" button, and choose the file rice.tif. Change the name for the output variable from ans to a, then press the "Execute" button. Two things should happen:

1. The image 'rice' is loaded into the variable a, and displayed to some figure window:



2. The following lines (or something very similar) appear in the command window:

```
>> a = readim('c:\matlab\toolbox\dipimage\images\rice.tif','')
Displayed in figure 1
```

This is to show you that the same would have happened if you would have typed that command directly yourself, without using the GUI. Try typing this command:

```
a = readim('rice')
```

The same image should be loaded into the same variable, and again displayed to some window. Note that we left off the '.tif' ending of the filename. readim can find the file without you having to specify the extension. We also didn't use the second argument to the readim function, since '' is the default value. Finally, by not specifying a path to the file, we asked the function to look for it either in the current directory or in any of the directories specified by the ImageFilePath setting (see Section 8.4).

To avoid having the image displayed in a window automatically, add a semicolon to the end of the command:

```
a = readim('rice');
```

3.3 Pre-processing the Image


You will have noticed the heavy background shading in this image. If we try to segment it directly, the results will be unsatisfactory (as you can try out later). Let's do some background correction. The idea is to use a low-pass filter that removes the objects while keeping the slow change in the background. Choose "Filters" and "Gaussian filter". Select a as the input image, and choose a name for your background image (we use bg). Finally, choose a suitable value for the filter parameter, such that the objects are removed and the background shading is left. Try different settings until you are satisfied with the result.

Once we have the background image, we can subtract it from the original image. It is very easy to do arithmetic with images in MATLAB. Type

```
a = a - bg
```

The new image should be displayed to a figure window, but it looks very dark. This is because the pixels have lower values now, some even have negative values. By default, images are displayed by mapping the value 0 to black, and the value 255 to white. You can change

this by choosing a different mapping mode. Open the "Mappings" menu on the figure window, and choose "Linear stretch" (try out the other modes too).



The "Actions" menu allows you to choose what the mouse should do on the figure window. Select "Pixel testing", and press the mouse button while pointing somewhere in the image (keep the button down). The figure caption changes to show the coordinates of the mouse in the image and the value of the pixel at those coordinates. Try moving the mouse while holding the button down. Another option on the "Actions" menu ("Zoom") is used to zoom in on an image. Try it out too. See Chapter 6 for more information on the figure windows.

The next step is to segment the image. We need to find some threshold that distinguishes the grains of rice from the background. To find it, we can examine the histogram of the image. Choose "Histogram" on the "Statistics" menu, or type

The graph shows two peaks, one for the background, one for the objects. Find a value in between for the threshold. To do the segmentation, compare all pixel values with the threshold, which can be done in this way:

$$b = a > 20$$

This results in a binary image (logical image, containing values of "true" and "false", coded as 1 and 0), with ones at the pixels that belong to the objects.

The final step is to remove the grains that do not completely lie inside the image. We can do this using a binary operation. Find and execute the "Remove edge objects" function in the menu system. What it does is the same as the **bpropagation** function, with an empty image as a seed image, and the edge condition set to 1. To create an empty seed image use the **newim** function. Thus, these two commands are equivalent:

```
b = b - bpropagation(newim(b,'bin'),b,0,2,1)
b = brmedgeobjs(b,2)
```

3.4 Measuring

Before we can start measuring, it is convenient to have a label image. Select the "Label objects" item on the "Transforms" menu, and select the new object image as the input. The result (name the image lab) is a labeled image where the pixels belonging to each object have a different value. In the window of the new image, select the "Labels" mapping. Now each



grey-value gets a different color. Examine the pixel values to see how the objects are labeled.

Now do the measuring. We will measure the object area in pixels ('size') and the Feret diameters ('feret'), which are the largest and smallest diameters, and the diameter perpendicular to the smallest diameter.

```
data = measure(lab,[],{'size','feret'});
```

measure returns an object of type dip_measurement, which is explained further in Chapter 5. Leaving the semi-colon off the previous command, the complete measurement results are displayed at the command prompt. Furthermore, data(1) is the measurement results for object with label 1, data.feret is an array containing all the Feret diameters, and data(1).feret are the Feret diameters for object number 1.

To extract the measurements done on all objects and put them in an array, type

```
feret = data.feret;
sz = data.size;
```

This gives us arrays with the measured data. MATLAB allows all kinds of statistics and analysis on these arrays. For example, mean(sz) gives the mean grain area.

We will use scatter to find some correlation between the diameters and the area of the grains. Let's start by plotting the length of the grains against their width:

```
figure; scatter(feret(1,:),feret(2,:))
```

Apparently, they are mostly unrelated. Let's try a relation between the length and the surface area:


```
scatter(feret(1,:),sz)
```

These appear to be more related, but, of course, the area also depends on the width of the grains. If we assume that the grains are elliptic, we know that the area is $\frac{1}{4}\pi d_1 d_2$. Let's plot the calculated area against the measured area:

```
scatter(sz,pi*feret(1,:).*feret(2,:)/4)
```

Wow! That is a linear relation. We can add a line along the diagonal to see how much the ratio differs from 1 (the other commands are to make the figure look more pretty):

```
hold on , plot([180,360],[180,360],'k--')
axis equal , box on
xlabel('object area (pixels^2)')
ylabel('\pi{\cdot}a{\cdot}b (pixels^2)')
```



The actual slope can be computed by:

```
f = sz'\calc'
```

(this is the lest-squares solution to the linear equation sz'*f = calc'; the apostrophes transpose the vectors to create column vectors).

3.5 Where to Go from Here

If you are new to MATLAB, it would be a good idea to read the "Getting Started with MATLAB" manual. If you are new to image processing, you can read "The Fundamentals of Image Processing", an online image-processing course, which can be found at: http://www.qi.tnw.tudelft.nl/DIPlib/docs/FIP.pdf.

Before you start using this toolbox, we recommend that you read Chapter 4 (at least Section 4.11). It contains very important information on the dip_image object and its usage. Since it is not the same as a regular MATLAB array, it can be a bit confusing at first.

The dip_image Object

Images used by this toolbox are encapsulated in an object called dip_image. Objects of this type are unlike regular MATLAB arrays in some ways, but behave similarly most of the time. This chapter explains the usage of these objects.

4.1 Creating a dip_image Object

To create a dip_image object, the function dip_image must be used. It converts any numeric array into an image object. The optional second argument indicates the desired data type for the image. The pixel data will be converted to this type if possible, or else an error will be generated (for example, it is illegal to convert complex data to a real type, since there are many ways this can be accomplished; it is necessary to do this explicitly). The valid data types are listed in Table 4.1. This table also lists some alternative names that are mapped to the names on the left; these are just to make specifying the data type easier.¹

For example,

```
a = dip_image(a, 'sfloat');
```

will convert the data in a to single (4-byte) floats before creating the dip_image object. The variable a now behaves somewhat differently than you might be used to. The following sections explain its behavior.

There are also some commands to create an image from scratch. newim is equivalent to the zeros function, but returns a dip_image object.

```
a = newim(256, 256);
```

creates an image with 256x256 pixels set to zero. If b is an object of type dip_image, then

```
a = newim(b);
```

creates an image of the same size (this is the same as newim(size(b))). The functions xx, yy, zz, rr and phiphi all create an image containing the coordinates of its pixels, and can be used in formulas that need them. For example, rr(256,256)<64 creates a binary image with a disk of radius 64. The expression

```
a = (yy('corner'))*sin((xx('corner'))^2/300)
```

generates a nice test pattern with increasing frequency along the x-axis, and increasing amplitude along the y-axis. All these functions have 256x256 pixels as the default output size, and allow as a parameter either the size of an image, or an image whose size is to be copied.

¹Note that these are the names of some additional DIP*lib* data types not used under MATLAB, the names MATLAB uses for the data types, and some generalizations of the other names.

Name	Description	Other allowed names
bin	binary (in 8-bit integer)	bin8, bin16, bin32
uint8	8-bit unsigned integer	
uint16	16-bit unsigned integer	
uint32	32-bit unsigned integer	uint
sint8	8-bit signed integer	int8
sint16	16-bit signed integer	int16
sint32	32-bit signed integer	int, int32
sfloat	single precision float	float, single
dfloat	double precision float	double
scomplex	single precision complex	
dcomplex	double precision complex	complex

Table 4.1: Valid data types for the dip_image object.

For example, a*xx(a) is an image multiplied by its x-coordinates.

Images can have any dimensionality, including 0 and 1, which are not allowed in MATLAB arrays. A 1-element numeric array is a special case of a two-dimensional array, whereas a 1-pixel image is seen as a zero-dimensional image. This has repercussions in the possible return values of size and ndims. For example, size will return an empty array for a zero-dimensional image, instead of the array [1,1]. For more information on image dimensionality, see Section 4.5.

4.2 Displaying dip_image Objects

When a MATLAB command does not end with a semicolon, the display method is called for the resulting values, if any. This method defaults to calling the disp method, which displays all the values in matrices. For the dip_image objects, the display method has been overloaded to call dipshow instead; dipshow displays the image in a figure window (see Section 7.2 for more information on this function). There is an exception for zero-dimensional and empty images, for which display always calls disp, and which will show information on the image.

The disp method shows only the image size and data type instead. If you want display to call disp instead of dipshow, you can change the 'DisplayToFigure' preference using dipsetpref (see Sections 7.8 and 8.4).

4.3 Operations on dip_image Objects

All mathematical operations have been overloaded for the dip_image object. The matrix multiplication (*), which is meaningless on images, does a pixel-by-pixel multiplication, just as the array multiplication (.*). The same applies to the other matrix operations. Relational operations return binary images. Binary operations on non-binary images treat any non-zero value in those images as true and zero as false. For example, to do a threshold we do not need a special function, since we have the relational operators:

```
b = a > 100:
```

			0	1 0 (, ,
abs	acos	angle	asin	atan	atan2
besselj	ceil	conj	cos	erf	exp
fix	floor	imag	log	log10	log2
mod	phase	pow10	pow2	real	round
sign	sin	sqrt	tan	xor	

Table 4.2: Arithmetic functions defined for objects of type dip_image(image in, image out).

Table 4.3: Arithmetic functions defined for objects of type dip_image (image in, scalar out).

all	any	max	mean	median	min
mod	percentile	std	sum		

A double threshold would be (note MATLAB's operator precedence):

```
b = a > 50 \& a < 200;
```

A note is required on the data types of the resulting images. The "higher" data type always determines this result, but we have chosen never to return an integer type after any arithmetic operation. Thus, adding two integer images will result in a 4-byte floating-point image; an 8-byte floating-point (double) image is returned only if any of the two inputs is double.

Many of the arithmetic functions have also been defined for objects of type dip_image (see Tables 4.2 and 4.3 for a complete listing). The basic difference between these and their MATLAB counterpart is that they work on the image as a whole, instead of on a per-column basis. For example, the function sum returns a row vector with the sum over the columns when applied to a numeric matrix, but returns a single number when applied to an image. Besides these, there are some other functions that are only defined for objects of type dip_image. See Section 4.10 to learn about these functions. That section also lists some functions that behave differently than usual when applied to images.

4.4 Indexing Pixels

In image processing, it is conventional to index images starting at (0,0) in the upper-right corner, and have the first index (usually x), index into the image horizontally. Unfortunately, MATLAB is based on matrices, which are indexed starting at one, and indicating the row number first. By encapsulating images in an object, we were allowed to redefine the indexing. We chose not to follow MATLAB's default indexing method. This might be confusing at first, and special care must be taken to check the class of a variable before indexing.

dip_image objects are indexed from 0 to end in each dimension, the first being the horizontal. It is, of course, also possible to index using a single index, in which case, following MATLAB's default behavior, the indices increase in the vertical direction, but start at 0 ($i = y + x \cdot \text{height}$). The size function also returns the image width as the first number in the array.

Any portion of a dip_image object, when extracted, is still a dip_image object, even if it is just a single pixel. To get a numeric array out of an image, use the double function (or dip_array, see Section 4.10). Thus, to get the value of a pixel in an image, type

```
b = double(a(0,0));
```

Table 4.4: Dimension manipulation functions.

cat	flipdim	fliplr	flipud	permute	repmat
reshape	rot90	shiftdim	squeeze		

Any numeric type can be assigned into a dip_image object, without changing the image data type (that is, the element assigned into the image is converted to the image data type). For example,

$$a(:,0) = 0;$$

sets the top row of the image in a to 0. Note that indexing expressions can become as complicated as you like. For example, to sub-sample the image by a factor 3, we could write

$$a = a(1:3:end, 1:3:end);$$

Finally, it is also possible to index using a mask image. Any binary image (or logical array) can be used as mask, but it must be of the same size as the image into which is being indexed. For example,

$$a(m) = 0;$$

sets all pixels in a, where m is one, to zero. A very common expression is of the form

$$a(a<0) = 0;$$

(which sets all negative pixels to zero).

Note that the expression a(m) above returns a one-dimensional image, with all pixels selected by the mask. Also, the expression a(:,0) does not return a 1D image, but a 2D image with a height of 1 (see Section 4.5). To obtain a 1D image use squeeze(a(:,0)).

4.5 Dimensions

The image in a dip_image object can have any number of dimensions. As in MATLAB, operations between two images require that both images have the same number of dimensions, as well as the same size. There is only one exception to this rule.

In MATLAB, dimensions with size 1 are called singleton dimensions. Singleton dimensions are always preserved, except at the end of the arrays. Thus, an array of size 4x1x6x1 is the same as an array of size 4x1x6. This is not the case for objects of type dip_image . These have all singleton dimensions preserved. However, it is possible to do arithmetic operations between two images with different number of trailing singleton dimensions (e.g. between two images with sizes 4x6x1 and 4x6). This is the exception to the rule mentioned above.

Functions used in MATLAB to manipulate dimensions have also been overloaded to do the same thing with images. They are listed in Table 4.4.

When extracting a portion of an image, the dimensionality is not lost either. Thus, if a is a 3D image, then a(:,:,2) and a(0,0,0) are too. However, they are displayed as if they were a 2D and 0D image, respectively. Using squeeze, these singleton dimensions are thrown away. squeeze(a(0,0,0)) is a 0D image.

4.6 Image Arrays

It is possible to join objects of type dip_image in an array, and the resulting array is still of type dip_image. However, an array of type dip_image is treated very differently throughout the interface. To support this idea, the functions class and isa, when querying an array of type dip_image, report that the object is of type dip_image_array. This is the recommended way of determining if the object is a single image or an array of images.

To create an array of images use the function newimar. It has two forms: in the first form, specifying the array dimensions creates an array of empty images; in the second form, two or more images are joined into an image array. These two examples show both forms:

```
A = newimar(3); % a 3-by-1 array of empty images
B = newimar(a,b,c); % a 3-by-1 array with images a, b and c
```

The images in an array do not need to be of the same size or type, since the dip_image_array object is just a collection of independent objects of type dip_image. Accessing any of those images is possible by indexing through the curly braces ({}). Continuing the example above,

```
c = B{3};

A{1} = a;
```

Note that indexing into the array does follow the standard MATLAB rules (starting at 1, first index is row number). It is possible to combine both types of indexing, but only in a fixed order, that is, the curly braces must come before the round braces:²

```
A\{1\}(0,0)
```

Most functions and operations do not work on objects of type dip_image_array, but the functions imarfun and iterate allow operations to be performed on all images in an array. See Section 4.10 for more information on these functions. The functions size and ndims behave differently when their input is an array of images. In this case, they work on the array itself, instead of on the images in it.

Concatenation of images does not produce an image array, but a larger image. Furthermore, concatenation of image arrays also produces a singe image, where the image arrays are first concatenated to form an image. For example,

```
d = [A];
is the same as
d = [A{1},A{2},A{3}];
```

If all the images in the array are of the same dimensionality and size, the array can be treated in a special way. We will call such an array a tensor image.

4.7 Tensor Images

A tensor image is a special kind of image array, in which all images are of the same dimensionality and size. If this is the case, **istensor** returns non-zero (true). For these special arrays, some arithmetic operations are defined: +, -, *, .* and ./. They are applied to the arrays in the expected way (that is, tensor by tensor, not image by image). The pixels of a

²This is a limitation of the MATLAB parser.

Table 4.5: Arithmetic functions defined for tensor images.

curl	det	divergence	eig_largest	eye	inner
inv	norm	outer	rotate	smooth	trace

tensor image can also be indexed, returning a new tensor image. To get the array at a single pixel, use the double function on it. For example, say A is a tensor image. Then $A\{1\}$ is an image with the first tensor component as pixel values, A(0,0) is a tensor image with a single pixel, and double(A(0,0)) is a MATLAB array with the tensor values at the first pixel. This indexing is not allowed on image arrays that are not tensors. Note that the functions size and ndims make no exception for tensor images, and work on the array itself, not on the images in it. Thus, they return the size and dimensionality of the tensors, not of the image. To get the size of the image, extract one of the images from the array and apply size to it:

$$sz = size(A{1});$$

Note that a scalar image (with one component) is also a tensor image (istensor returns true). Additionally, the function isvector returns true if the tensor image has more than one component and these are all along one dimension.

Functions defined specifically for tensor images are summarized in Table 4.5. See Section 4.10.

4.8 Color Images

A color image is represented in a dip_image object by a tensor image with some extra information on the color space in which the pixel values are to be interpreted. A color image must have more than one channel, so the tensor image that represents it should have at least two components. Use the colorspace function (see Section 4.10) to add this color space information to a tensor image:

```
C = colorspace(A,'RGB')
```

A color space is any string recognized by the system. Currently defined color spaces are RGB, R'G'B', XYZ, Yxy, L*a*b*, L*u*v*, CMY, CMYK, HCV and HSV. It is possible to specify any other string as color space, but no conversion of pixel values can be made, since the system wouldn't know how. Images with a color space will be displayed by dipshow. If the color space is recognized it will be converted to RGB for display.

To convert an image from one color space to another, use the colorspace function. Converting to a color-space-less tensor image is done by specifying the empty string as a color space. This action only changes the color space information, and does not change any pixel values. Thus, to change from one color space to another without converting the pixel values themselves, change first to a color-space-less tensor image, and then to the final color space.

The function joinchannels combines two or more images into a color image using the specified color space:

```
C = joinchannels('RGB',a,b,c)
```

All operations that are defined for tensor images can be applied to color images. In case a dyadic operation is applied to two color images with different color spaces, no conversion is done. Instead, the color space information is thrown away and both images are treated

as tensor images. An operation between a color image and a tensor image produces a color image.

4.9 A Note on the end Method in Indexing

Because of limitations in the MATLAB language, it is impossible to know, for the overloaded end method, if it is being used inside curly or round braces (i.e. whether the last element of the image array is requested, or the last pixel of the image is requested). The solution we have adopted is to suppose image array indexing if the object being indexed is an array, or pixel indexing otherwise. Thus, end only works fine inside curly braces if there is more than one image in the object, and it only works fine inside round braces if there is just one image in the object.

Since this is not an optimal solution, we suggest that you use end with care. end can be substituted with size or length in all cases. These two

```
a{end}, b(end,end)
are equivalent to
a{length(a)}, b(size(b,1)-1,size(b,2)-1)
```

4.10 Special Functions

There are some special functions defined only for dip_image objects. Many have already been mentioned in preceding sections, but we will summarize them here. We also list some functions that are very different in usage from their MATLAB equivalent.

cat

cat concatenates images into a larger image, just as the regular cat does with arrays. The difference is that it concatenates any image array parameters into a single image before joining its parameters. Thus, it always produces a single image (see Section 4.6).

colorspace

This function will add and retrieve color space information from a tensor image with two or more components. It can also be used to change the color space of a color image, in which case the pixel values will be recomputed. See Section 4.8 for more information on color spaces.

curl

Calculates the rotation of a 2D or 3D vector image.

datatype

datatype extracts the data-type string from a dip_image object. If the input is an image array, it expects as many output parameters as images are in the array. The string returned is a DIPlib data type name, not a MATLAB class name (i.e. 'sfloat', not 'single'); see Table 4.1. To change the data type of an image, use the function dip_image.

dip_array

dip_array extracts the data array from a dip_image object. If the input is an image array, it expects as many output parameters as images are in the array. The data array is not converted to any specific type. If you want to convert the data, use double, uint8 or any of the other basic data type constructors.

divergence

Calculates the divergence of a vector image.

double, single

These functions convert a scalar image (in an object of type dip_image) to a MATLAB array of type double (MATLAB's default data type) or type single (single precision floating point). If the object contains a tensor image with a single pixel, an array is returned with the tensor values.

Also defined are uint8, uint16, uint32, int8, int16 and int32. These don't accept any form of tensor image.

eig_largest

This function computes the largest eigenvector for a square tensor image using the Power method. An optional second output argument contains the corresponding eigenvalue.

The second argument in the call

```
v = eig_largest(a,sigma)
```

specifies the tensor smoothing that should be applied before calculating the eigenvector.

findcoord

findcoord returns the coordinates of the pixels with non-zero values:

I = findcoord(b)

returns an array with as many columns as dimensions in b, and one row for every non-zero pixel. Note that this matrix cannot be used directly to index an image; each row should be used separately: b(I(n,1),I(n,2)).

findcoord is similar to find, in that it returns the same list of pixels, but in a different form.

gradient

This function returns the gradient vector of a real image. Its second parameter is the sigma of the Gaussian gradient filter. The output vector image has N components, where N is the dimensionality of the input image, and each component is an image with the same size as the input.

imarfun

imarfun applies some other function on an array of images. It has two modes.

In the first mode, it produces a numeric array with the same size as the input image array,

Table 4.6: Options for imarfun in its first form.	These operations compute a single value for
each image in the array.	
Option Meaning	

Option	Meaning
'isempty'	true for empty image
'islogical'	true for binary image
'isreal'	true for non-complex image
'ndims'	number of dimensions of image
'prodofsize'	number of pixels in image
'max'	maximum pixel value in image
'mean'	mean pixel value in image
'median'	median pixel value in image
'min'	minimum pixel value in image
'std'	standard deviation of pixels in image
'sum'	sum of pixels in image

Table 4.7: Options for imarfun in its second form. These operations combine all images into a new image.

Option	Meaning
'imsum'	sum of all images
'improd'	product of all images
'imor'	true if any pixel is non-zero
'imand'	true if all pixels are non-zero
'immax'	maximum pixels over all images
'immin'	minimum pixels over all images
'imeq'	true if pixel is equal in all images
'imlargest'	index of first image with largest pixel value
'imsmallest'	index of first image with smallest pixel value

where each number is some measure for each image. The possibilities are listed in Table 4.6. This example replaces the image **a** for the empty images in the array **A**:

```
I = imarfun('isempty',A);
A{find(I)} = a;
```

The second mode applies an operation to all images in the array, which must all be of the same size (istensor returns true), producing an image with the same size as the images in the array. The possibilities are listed in Table 4.7. For example, to get the sum of all images in the array A, we can do either of these:

```
res = imarfun('imsum',A);
res = A{1}+A{2}+A{3}+...+A{end};
```

inner, outer

These calculate the inner and outer product of two tensor images. outer is only defined for tensors with three components.

iscolor

iscolor returns true if the input image is a tensor image and contains color space information (see Section 4.8).

istensor

istensor returns true if all images in an image array are of the same size. A tensor image is treated differently than a regular image array (see Section 4.7).

isvector

isvector returns true if the image pixels are represented by vectors, that is, the image array is one-dimensional and has more than one component (see Section 4.7).

iterate

iterate loops through each image in the image arrays it gets as input, and calls the function fun with the given parameters. This is a very versatile function, and allows a combination of image arrays, single images and other objects as input. The only requirement is that all the image arrays are of the same size.

For example, let A and B be N-by-M dip_image_array objects. Then

```
C = iterate('max',A,B);
is the same as
C = newimar(N,M);
for ii=1:N*M, C{ii} = max(A{ii},B{ii}); end
```

Use the function iterate to apply filters to color images.

max, min

These functions have two different forms.

In the first form, they return the global maximum/minimum in the image and, optionally, its position:

```
[value,pos] = max(a);
```

It is also possible to process only a specified set of dimensions. For example, this command returns a 1D image (assuming a is 3D), where each pixel i contains the maximum over a(i,:,:):

```
value = max(a, [], [2,3]);
```

The second form takes two images and returns an image with the supremum of the two:

```
c = max(a,b);
```

mean, std

These return the mean intensity or standard deviation of the pixel values in an image. It is possible to add a mask:

```
value = mean(a,m);
```

As in max, it is possible to specify a set of dimensions that are to be processed:

```
value = mean(a, [], [2,3]);
```

percentile

To complement the functions max, median and min, percentile returns the p percentile of all pixels in the image a:

```
value = percentile(a,p);
```

Note that percentile(b,50) is exactly the same as median(b), percentile(b,0) is a silly way of computing min(b), and percentile(b,100) is a silly way of performing max(b).

This function also allows specifying a set of dimensions that are to be processed:

```
value = percentile (a,p,[],[2,3]);
```

phase

phase is defined the same as angle, and is provided because it might be easier to remember for some users. It returns the angle of the complex values in an image.

pow10

This function was added just to complete MATLAB's collection of pow2, log2, and log10.

rotate

The overloaded method rotate has nothing to with MATLAB's rotate. Applied to a 3D-vector image, it rotates the vectors around an axis given by a second vector image or vector.

smooth

smooth(a, sigma) applies tensor smoothing to the tensor image a. sigma defaults to 1.

4.11 Review of the Differences Between a dip_image and a MATLAB Array

As we have seen, objects of type dip_image have some differences with respect of regular MATLAB arrays. The main difference is in indexing. We start counting pixels from 0, and the first index counts from left to right. This ordering is also used by functions such as size, in which the first number is the image width and the second one the height. Finally, ndims can return 0 or 1, which it never does for MATLAB arrays, and size can return an empty array or a scalar, which it never does for MATLAB arrays. The reason is that zero-dimensional and one-dimensional images are allowed, and are not seen as a special case of two-dimensional images. Furthermore, singleton dimensions at the end are not ignored.

When a MATLAB command results in an object of type dip_image, and it is not ended with a semicolon, the image is displayed to a figure window, instead of having its pixel values shown in the command window. This is the default behavior, but can be overridden.

There are no array operators for scalar images, all operators work on a pixel-by-pixel basis. All functions that work on the columns of numeric arrays work on the image as a whole when

applied to a dip_image object.

A collection of images can be stored in an object of type dip_image. For the purposes of the toolbox, such an object is called a dip_image_array. Syntax for indexing into such a collection is similar to that used to index into a cell array (which is a collection of any type of arrays), but should not be confused for one. A special type of image array is used as a tensor image, for which a whole range of functions is available. Color images are tensor images with color space information.

Objects of type dip_image cannot be used in functions of the MathWorks' Image Processing Toolbox. Although most of MATLAB's functions work on dip_image objects, not every function will work as expected. Use the functions double or uint8 to convert the image to a format recognizable by these functions.

The dip_measurement Object

The function measure (and the low-level dip_measure function in DIP lib) returns the measurement results in an object of type dip_measurement. It contains all the measures done on an image in a manageable way.

5.1 Extracting Measurement Data

The data in the dip_measurement object can be accessed in a very simple way, but only for reading, not writing (i.e. data manipulation is not allowed).

Indexing with parentheses is used to access the measurements belonging to one or more objects. The index used must match the label ID of the object in the image, and the returned value is an object of type dip_measurement.

The dot operator is used to extract the values corresponding to a single measurement. The array returned is of type double.

For example,

```
msr(11:15).size
```

will return a double array with five elements, being the sizes for objects number 11 through 15. Note that element 11 doesn't need to be placed 11th in the list of measurements. If only objects starting at 10 were measured, the above example is equivalent to

```
msr.size(2:6)
```

since msr.size returns a double array, whose second element would be the size of object number 11.

The end method will return the last label ID in the object. double converts the data in the object to a double array, loosing the names of the measurements and the label IDs.

5.2 Other Information on the dip_measurement Object

Besides extracting the measured data, you might want to gain more knowledge on the object you are dealing with (e.g. which measurements were taken and how many of them are there). This section describes functions used for this purpose.

fieldnames returns the names of the measurements present in the object.

isempty returns true if there is no data in the object.

size returns the number of IDs as the first dimension, and the number of measurements as the second. Note that the number of measurements returned by size does not need to be

equal to the number of names returned by fieldnames. If a measurement contains more than one value for each object, each of these is taken as a measurement. Thus, the number of measurements is the number of scalar values assigned to each object. size(double(msr)) returns the same value as size(msr).

5.3 Combining Measurement Data

To join measurements produced by different calls to measure, use the default MATLAB syntax. However, there is the limitation that, when joining measurements, they must contain either the same measurements on different objects, or different measurements on the same objects. Horizontal and vertical catenations produce different effects.

[A,B] joins two measurement objects with the same label IDs, but different measurements. If some measurements are repeated, or if the label IDs don't match, an error is generated.

[A;B] joins two measurement objects with the same measurements, on different label IDs. If some IDs are repeated, or if the measurements don't match, an error is generated.

In some cases, objects in different images have the same labels. These need to be changed before catenation is possible. This is done by the following syntax:

```
msr.id = 51:73;
```

The length of the array assigned to the IDs must have the same number of elements as the measurement object.

Similarly, it is possible to measure the same thing on different images of the same objects. For example, one might measure the average grey-value on all three channels of an RGB image. To join these measurements into a single object, it is possible to add a prefix to the names of the measurements:

```
msr1.prefix = 'red_';
msr2.prefix = 'green_';
msr3.prefix = 'blue_';
msr = [msr1,msr2,msr3];
Note that this prefix cannot be changed, only added to. For example,
msr.prefix = 'A';
msr.prefix = 'B';
```

causes the measurements in msr to have names like 'BAsize'.

5.4 Converting a dip_measurement Object to a dataset Object

The dip_measurement object provides an overloaded version of the dataset function, which will convert the measurement object into a PRTOOLS data set. An optional second argument allows giving each object a class ID:

```
ds = dataset(msr, [1,1,1,2,2,3,2,3,3,2,1])
```

For more information on the PRTOOLS pattern recognition toolbox, go to http://www.qi.tnw.tudelft.nl/~bob/PRTOOLS.html.

5.5 Creating a dip_measurement Object with Your Own Data

To create an object of type dip_measurement, use the dip_measurement function. Its syntax is:

```
msr = dip_measurement(id, 'msrname1', msr1, 'msrname2', msr2,...)
```

where id is a vector containing the object IDs, and 'msrname1' and msr1 are the name and results of a measurement. The number of columns in msr1 should match the number of elements in id, as each of the columns represents the result of a measurement on a single object.

If the name of a measurement is not given, 'dataX' is assumed, where the 'X' is the ordinal number of the measurement. If id is not given, 1:N is assumed. Note that the only way it is possible to recognize whether id is missing is if the first argument is a string.

5.6 Backwards Compatibility

The dip_measurement object is new to version 1.1 of the toolbox. However, it has been implemented in such a way that most old code doesn't break. The structure that used to be returned by measure in earlier versions can still be obtained with the struct function:

```
oldmsr = struct(msr);
```

The dip_measurement constructor can be used to convert this structure back to an object. Converting to a structure is the only way of manipulating the measurement data.

Figure Windows

The display is a very important part of any image-processing package. dip_image objects containing scalar or color images with 1 to 3 dimensions are displayed to MATLAB's figure windows. These windows are completely cleared beforehand, meaning that images never share a window with each other or with other graphical elements. This chapter describes the possible interactions with figure windows, how to link variables with them, and their placing on the desktop.

6.1 The Figure Window Menus

The display for an image contains four menus: "File", "Sizes", "Mappings" and "Actions".

The first menu contains a "Save display..." option that saves the display to a TIFF file. This allows you, for example, to save an image with labels, or to zoom into a portion of an image and only save that. It also contains a "Close" and a "Clear" item. On Windows machines, there is a "Copy display" option. It does the same as "Save", but writes the image as a bitmap to the clipboard, so that it can be pasted into other applications.

"Sizes" contains options that call diptruesize, which causes the image to be displayed with an aspect ratio of 1, and various different zoom factors (see Section 7.4). It also contains an option that causes a the image to be stretched to fill the figure window. The last option on this menu, "Default window size" resizes the window to some pre-defined size (which is 256 by 256 pixels, but you can change it using dipsetpref, see Sections 7.8 and 8.4).

"Mappings" contains different ways of mapping the data for display. These options correspond to calls to dipmapping (see Section 7.3). The first section here contains stretching modes, which correspond to the range parameter in dipshow (see Section 7.2); one of these options is "Manual...", which, through a dialog box, allows the user to select a custom range. The second section, only available for grey-value images, selects a colormap. The options in the first section will sometimes change the selection of the colormap. If the image being displayed is complex, this menu allows choosing the complex to real mapping performed (magnitude, phase, real or imaginary part). For 3D images you can select the orientation of the slices shown (X-Y, X-Z or Y-Z), as well as decide whether the stretching mode selected is to be computed on the whole volume ("global") or only on the current slice.

The "Actions" menu selects the actions that can be performed through the mouse. The options "none", "Pixel testing", "Zoom", "Looking glass" and "Pan" (which correspond to the diptest, dipzoom, diplooking and dippan commands) are available to all image types. The 3D image display also contains an option to "Step through slices" (dipstep), and the 2D grey-value-image display contains an option for "Orientation testing" (diporien). See

Section 6.2 for more information on these modes, and Section 7.5 for the associated commands. This menu also contains a command to enable or disable the keyboard functionality in the window. See Section 6.3 for more information on this.

Finally, the "Actions" menu on 3D images contains some more options:

- "Link displays" (diplink, see Section 7.6) allows the user to link a 3D display with other 3D displays. When stepping through the slices of this image, or changing the orientation of the slicing, the images in the other displays will be kept in sync. This can be used to easily compare various 3D images.
- "Animate" (dipanimate) will step through all slices in sequence. Calling this function from the command line allows the user to choose the speed of this animation.
- "Max projection" and "Sum projection" (dipprojection) open a new window with the chosen type of projection, along the current visualization axis.
- "Isosurface plot" (dipisosurface) also opens a new window, showing an isosurface plot of the image. This window contains some controls to modify the surface. You should be aware that it takes a while to generate an isosurface. It is recommended to smooth and down-sample an image before generating an isosurface plot.

6.2 Using the Mouse in Figure Windows

As discussed above, the "Actions" menu allows selecting a mode for the mouse to work in. Depending on the dimensionality and type of the image, the modes are (the commands between brackets can also be used to turn these modes on and off, see Section 7.5):

- "None": The mouse does nothing.
- "Pixel testing" (diptest): The mouse is used to examine pixel values and location.
- "Orientation testing" (diporien): The mouse is used to examine local orientation.
- "Zoom" (dipzoom): The mouse is used to zoom the image in and out.
- "Looking glass" (diplooking): The mouse is used to enlarge a part of the image.
- "Pan" (dippan): The mouse is used to pan the image if it doesn't fit in the window.
- "Step through slices" (dipstep): The mouse is used to step through the slices of a 3D volume.

When diptest is turned on, depressing the left mouse button will cause the current cursor position to be displayed in the title bar, together with the grey-value (or color values) of the pixel at that location. It is possible to move the mouse while holding down the button. Depressing the right mouse button does the same thing, but the cursor position becomes the origin of the coordinate system. This mode allows for length measurements in images.

When diporien is first turned on, a dialog box asks for the orientation image to associate to the currently displayed image. This dialog can also calculate that image for you, using the function structuretensor. Depressing any mouse button over the image now converts the cursor into a line, aligned with the local image orientation. Like in diptest, the title bar changes to display the coordinates and local orientation. The only way of changing the orientation image associated with this display is to set "Actions" to "None", and then enable

diporien again. Displaying a new image in this display also removes the orientation image. When dipzoom is turned on, the mouse can be used to zoom the image in and out:

- Clicking with the left mouse button zooms the image in (with a factor 2).
- Clicking with the right one will zoom the image out (with a factor 2).
- Double-clicking any mouse button will cause the image to be stretched to fill the figure window.
- Dragging a rectangle around an area of interest will cause it to be zoomed-in on.

The aspect ratio is set to 1:1 when zooming in or out, except after double-clicking. See Section 6.3 to learn how to zoom using the keyboard.

dippan enables the user to use the mouse to pan (move) the image if it is larger than the window. Just press the left mouse button and move the mouse with the button down. It is also possible to pan using the keyboard (see Section 6.3).

When dipstep is selected, it allows the user to click or drag the cursor over the image to go back and fourth through the slices that make up the 3D volume. Moving the mouse down or to the right (while holding down the left button) displays higher slice numbers. Moving the mouse up or to the left displays lower slice numbers. Alternatively, click with the left mouse button to go up, and with the right one to go down. Section 6.3 explains how to do this with the keyboard.

6.3 Using the Keyboard in Figure Windows

When the keyboard is enabled for a display window, it can be used to step through the slices of a 3D image, zoom in and out, and pan the image. These functions are independent of the chosen mode for the mouse under the "Actions" menu.

The keys N and P step to the next and previous slice, respectively, of a 3D image. Additionally, you can type the number of a slice and press **Enter** to go to it. Note that slice numbers start with 0.

The keys I and O are used to zoom in and out, respectively. The zoom factor is 2. When zoomed in, use the following keys to pan the image and get to the area of interest: W for up, S for down, A for left, and D for right. With MATLAB 6 and newer, it is also possible to use the arrow keys.

The **Esc** key disables the keyboard. This is useful under Windows, where displaying an image causes its window to gain keyboard focus. You would have to click on the command window to continue typing a new command. Instead, press **Esc**, which disables the keyboard for the window and causes your keystrokes to be send to the command window. To enable the keyboard again, use the menu item "Enable keyboard" under the "Actions" menu. With the command

dipsetpref('EnableKeyboard', 'off')

you disable the keyboard by default, and will have to use the above mentioned menu item to enable it. See Sections 7.8 and 8.4.

6.4 Linking Variables with Figure Windows

A variable name can be linked with the handle of a figure window, such that any image stored in that variable will always be displayed in the same window. This is done through the dipfig function (see Section 7.7). It is not possible to link a single variable with more than one figure window, but it is possible to link many variables to the same figure window. This system allows the user to create a series of figure windows that will be reused, instead of having new windows created all the time. These links do not, however, promise that an image displayed is actually up-to-date. Changing the contents of a variable does not change the contents of a figure window. By not adding the semicolon at the end of commands, it is possible to automatically update the figure windows (see Section 4.2).

A special name 'other' is defined in dipfig, that is a substitute for all variables not explicitly linked to a figure window. It allows the user to have a window for all possible images he can create. 'other' can be linked to a series of windows, which then will be used sequentially.

Closing a window does not destroy the links that were made for it. Since variable names are linked to window handles, a window can be reopened to display the image with which it is linked.

Note that many toolbox functions that require a figure window handle as input also accept a variable name. Variable names linked with a figure window are considered aliases for a figure window handle.

6.5 Setting the Position of Figure Windows

The position of a figure window can be changed by manipulating its 'Position' property, which is defined by an array with four values: left, bottom, width and height.

```
set(handle, 'Position', [left, bottom, width, heigth]);
```

The coordinates for figure windows start at the bottom-left corner of the screen, and are in screen pixels by default. This can be changed to centimeters, inches and other units:

```
set(handle,'Units','points');
```

See "MATLAB Function Reference" for more information on figure window properties.

The dipfig function has an additional optional parameter, which can be used to set the position of a figure window at the same time that it is created. This parameter comes at the end of the parameter list, and is the same array used for the 'Position' property:

```
dipfig('a', [400,600,256,256]);
```

The width and height values are those of the image that will fit in the window, and the window itself is drawn around this area. These values are always in screen pixels.

If an image is larger or smaller than the size of the window, the window will be resized so that the image fits exactly. That is, unless the 'TrueSize' option is turned off (see Section 8.4), in which case the window will not be resized, and the image will be stretched to fit. To have your windows fixed on the desktop, disable the 'TrueSize' option.

As with all other settings, the position of the figure windows cannot be saved from one session to the next. Add the appropriate commands to your startup.m or dipinit.m files to have

the same settings across sessions (see Section 8.3).

Toolbox Functions

7.1 The GUI: dipimage

The GUI is started with the dipimage command. It contains menus with all available image-processing functions in the toolbox. After choosing any of these menu items, the GUI window transforms itself into a dialog box so that you can enter the appropriate parameters. The controls that allow entering images have a context-menu (obtained by right-clicking in them) with the names of the images currently defined. It is possible to enter the name of a variable containing an image or any valid MATLAB statement that evaluates to image data. (The same is true for other objects, like measurements or data-sets. Also, the window selection control, which is a drop-down list, can be updated through its context-menu.) Pressing the "Execute" button causes the function to be called. There is also a button to get help on the particular function. The whole process is rather obvious and self-explanatory, and no further words shall be wasted on it.

7.2 The dipshow Function

dipshow shows a dip_image object, as an image, in a figure window (that is, as long as it is a binary, grey-value or color image, and has between 1 and 3 dimensions). An optional second argument indicates the display range required, and allows more flexibility than the options in the "Display" menu. The general form for dipshow is:

dipshow(a,range,colmap)

where range is either a grey-value range that should be displayed, or one of 'log' or 'base'. A range is a numeric array with two values: a lower and an upper limit. The pixels with the same or a lower value than the lower limit will be mapped to black. The pixels that are equal or larger than the upper limit will be mapped to white. All other values are linearly spaced in between. The strings 'lin' and 'all' and the empty array are a shortcut for [min(image),max(image)], and cause the image to be stretched linearly. The string 'percentile' is a shortcut for [percentile(image,5) percentile(image,95)], and 'angle' and 'orientation' are equivalent to [-pi,pi] and [-pi,pi]/2 respectively. The default range is [0,255], which is used unless a range is given explicitly. colmap is a colormap. It can either be 'grey', 'periodic', 'labels' or an array with 3 columns such as those returned by the MATLAB functions hsv, cool, summer, etc. (see the help on colormap for more information on this).

The strings 'angle' and 'orientation' imply 'periodic' if no explicit colormap is given. This colormap maps both the maximum and minumum value to the same color, so as to hide

a jump in angle or orientation fields. The string 'labels' implies a range of [0,255], and produces a colormap that gives each integer value a distinct color.

The string 'log' causes the image to be stretched logarithmically. 'base' is a linear stretch that fixes the value 0 to a 50% grey-value.

Examples:

```
dipshow(a,'lin',summer(256))
dipshow(a,[0,180],'periodic')
```

If the input argument is a color image, it will be converted to RGB for display.

The image is displayed in a figure window according to the name of the variable that contains the image. Links can be made using the dipfig function (see Section 7.7). If the variable name is not registered, a new figure window is opened for the image. To overrule this behavior, it is possible to specify a figure handle in the parameter list of dipshow:

```
dipshow(handle,image,'lin')
```

Finally, an optional argument allows you to overrule the default setting for the 'TrueSize' option. By adding the string 'truesize' at the end of the parameter list for dipshow, you can make sure that diptruesize is actually called. The string 'notruesize' does the reverse.

See Chapter 6 for more information on the figure windows used by dipshow.

7.3 Figure Window Support: dipmapping

The function dipmapping can be used to change the image-to-display mapping. All menu items under the "Mappings" menu are equivalent to a call to dipmapping. In a single command, you can combine one setting for each of the four categories: range, colormap, complex-to-real mapping, the slicing direction and the global stretching for 3D images.

```
dipmapping(h,range,colmap,torealstr,slicingstr,globalstr)
```

changes the mapping settings for the image in the figure window with handle h. It is not necessary to provide all four values, and their order is irrelevant. range can be any value as described for dipshow in Section 7.2: a two-value numeric array or a string. colmap can contain any of the strings described for dipshow, but not a colormap. To specify a custom colormap, use dipmapping(h,'colormap',summer(256)). torealstr can be one of: 'abs', 'real', 'imag' or 'phase'. slicingstr can be one of: 'xy', 'xz' or 'yz'. globalstr can be one of 'global' or 'nonglobal'. If you don't specify a figure handle, the current figure will be used.

Additionally, you can specify a slice number. This is accomplished by adding two parameters: the string 'slice', and the slice number. These must be together and in that order, but otherwise can be combined in any way with any of the other parameters. The same is true for the m'colormap' parameter.

7.4 Figure Window Support: diptruesize

The "Sizes" menu contains some options to call diptruesize (see Section 6.1). This function causes an image to be displayed with an aspect ratio of 1:1, each pixel occupying one screen

pixel. An argument gives the zoom factor. For example, 200 would make the image twice as large on the screen, but with the 1-to-1 aspect ratio:

```
diptruesize(200)
```

diptruesize('off') causes the image to fill the figure window, possibly loosing the aspect ratio. diptruesize accepts a figure handle as an optional first argument. If you provide a handle, you must also provide a zoom factor.

7.5 Figure Window Support: diptest, dipzoom, et al.

As explained in Section 6.1, the first section of items under the "Actions" menu correspond to the diptest, diporien, dipzoom, diplooking, dippan and dipstep commands. We explain here how to use the functions. The modes they activate are described in the section previously referred to.

All five functions have the same syntax:

```
diptest on
enables the mode, and
diptest off
```

turns it off. diptest, by itself, toggles the state. The current window is the last one activated. You can select a window either through some mouse action on that window, or by typing in the MATLAB command window:

```
figure(handle)
```

where handle is the handle of the figure window, which should be visible on the title bar. If you know this handle, you can also directly use it as a parameter to diptest:

```
diptest(handle)
or
  diptest(handle,'on')
```

7.6 Figure Window Support: diplink

diplink is the command that corresponds to the "Link displays..." menu option for 3D images (see Section 6.1). It is used in much the same way as the functions in Section 7.5. When turning on, it displays a dialog box that allows the user to select the windows with which to link. Alternatively, it is possible to specify the figure windows with which to link through the command line:

```
diplink('a',{'b','c','d'})
or
  diplink(1,[2,10,6])
```

7.7 Creating, Linking and Clearing Figure Windows: dipfig and dipclf

The single most important thing that can be customized in the DIP *image* environment is the way that images are displayed to figure windows. It is possible to link a variable name with a figure handle, such that that variable is always displayed in that same window. If a variable is not linked to any window, a new one will be opened to display it. The command

```
dipfig a
```

opens a new figure window and links it to the variable named a. Whenever that variable (if it contains an image) is displayed, it will be send to that window. If the window is closed, it will be opened again to display the variable. It is possible to link more than one variable to the same window, like in the next example (which uses the functional form):

```
h = dipfig('a')
dipfig(h,'b')
```

Finally, there is a special variable name, 'other', that creates a link for all variables not explicitly linked to a window. It is possible to have many windows linked to this special name, and they will be used alternately. Creating a window for 'other' avoids the opening of new windows for 'unregistered' variables.

To remove the links, type

```
dipfig -unlink
```

Unlinking only a specific variable is not implemented.

To clear all figure windows (for example at the beginning of a demo), use the function dipclf. It doesn't change the position or size of any window, but removes the images in them. dipclf can also be used to clear selected windows by giving it an array with handles or a cell array with names as an argument (in a cell array you can actually combine numeric handles and variable names).

7.8 Toolbox Preferences: dipsetpref and dipgetpref

All toolbox preferences are stored in memory, and are only accessible through the dipsetpref and dipgetpref functions. They are listed in Section 8.4.

```
v = dipgetpref('name');
```

retrieves the value of the named preference. Two special forms print all current preferences and all factory settings to the command window:

```
dipgetpref
dipgetpref factory

Setting a preference is similar:
    dipsetpref('name', value)

Furthermore, it is possible to set many preferences at once:
    dipsetpref('name1', value1, 'name2', value2, 'name3', value3,...)
```

7.9 Interactive Tools: dipcrop, dipgetcoords, et al.

These are some tools that, using an image display, allow the user to select points or regions in an image. dipgetcoords returns the coordinates of one or more points selected by clicking on an image. dipcrop returns a rectangular portion of an image selected by dragging a rectangle. dipprofile returns a 1D image interpolated along a path selected by the user on the display. diproi returns a mask image (ROI stands for region of interest) created by selecting the vertices of a polygon; it can only be used with 2D images.

dipgetimage retrieves the image from a display. Use it if you lost an image but can still see it in its display.

7.10 Image Processing Functions

The largest part of the toolbox is made out of the image processing functions. Most of them are listed in the menu system of the GUI, and all are listed by typing

```
help dipimage
```

The usage of each function can be retrieved through the help command or through the GUI.

7.11 Adding Functions to the GUI

To add a function to the GUI, it must:

- respond in certain ways to certain inputs, so that the GUI can query it for parameters, and
- be on both the MATLAB path and the DIP image path.

The second requirement is the easiest. If you have your functions in a directory called /myhome/mytools/, then these two commands accomplish it:

```
addpath('/myhome/mytools')
dipsetpref('CommandFilePath','/myhome/mytools')
```

The first requirement is a bit more complicated. To add this functionality to your own function, copy the code in Figure 7.1. It shows a complete skeleton for a function. The line that is not written-out is the one that assigns a structure into paramlist. This structure is the most complicated part of the function (Figure 7.2 shows an example), but allows both the automatic parsing of the input parameters and the drawing of the dialog box in the GUI. Automatic parameter parsing is discussed in Section 7.12.

The parameter structure paramlist contains four values:

```
menu Name of the menu to place the function in (string).

display Name for the function in the menu (string).

Structure array with input parameters.

Structure array with output parameters.
```

The function will be added to the end of the menu specified (in alphabetical order). If you want to change the order of the menu items, you will need to create a localdipmenu function (see Section 8.2).

```
function out = func_name(varargin)
% The next line defines the parameters your function requires
paramlist = struct(...);
% The next section causes this function to be integrated in
% the menu system
if nargin == 1
    s = varargin{1};
    if ischar(s) & strcmp(s,'DIP_GetParamList')
        out = paramlist;
        return
    end
end
% Below, add your own code
out = process_image(varargin);
```

Figure 7.1: Skeleton GUI function.

paramlist.inparams defines the input parameters, and contains the following fields for each parameter:

```
name Variable's name (string). Not used (for now).

description Description to show the user (string).

type Expected data type (string).

dim_check Required dimensionality.

range_check Expected range.

required 1 or 0, to specify whether the default value is useful.

default Default value to use if the parameter is not given.
```

paramlist.outparams defines the output parameters, and contains the following fields for each parameter:

```
name Variable's name (string). Not used (for now).

description Description to show the user (string).

type Data type (string).
```

The parameter description depends on the parameter type. What each of dim_check, range_check and default mean depends on the type. Also, each parameter type produces different controls in the GUI. Recognized types are listed below. Please examine any of the functions in the toolbox that put themselves on the menu to learn more about this structure.

'image'

An object of type dip_image. Other numeric arrays are converted to dip_image. The GUI presents an edit box where you can type any expression. Furthermore, a right-click in this edit box brings up a list with variables of class dip_image defined in the base workspace.

default is a string to be evaluated in the base workspace (therefore, you can use any expression with names of variables in the base workspace). Typically you would use 'a' or 'b' as a

```
inparams = struct(...
    'name',{'image_in','percentile','filterSize','filterShape'},...
    'description',{'Input image','Percentile','Size of filter',...
                    'Shape of filter'},...
    'type',{'image','array','array','option'},...
    'dim_check', {[], 0, 1, 0}, ...
    'range_check', {[], [0,100], 'N+', {'rectangular', 'elliptic',...
                    'diamond', 'parabolic'}},...
    'required', {1,0,0,0},...
    'default', {'ans', 50, 7, 'elliptic'}...
);
outparams = struct(...
    'name',{'image_out'},...
    'description',{'Output image'},...
    'type',{'image'}...
);
paramlist = struct(...
    'menu', 'Filters',...
    'display', 'Percentile Filter',...
    'inparams', inparams, ...
    'outparams', outparams...
);
```

Figure 7.2: Sample parameter structure (belongs to the function percf).

default value, and set required to 1. This way, the GUI shows the name of a variable possibly containing an image, but at the command-line (assuming you use automatic parsing) this default value is never used. It is also possible to specify something like [1,1,1;1,1,1;1,1,1] as a default image (as does the function convolve).

dim_check and range_check are ignored. Set them to empty arrays, for in the future these might be used to specify the type of image required.

'measurement'

An object of type dip_measurement. The same comments are valid as for 'image'.

'dataset'

An object of type dataset (from PRTOOLS). The same comments are valid as for 'image'.

'array'

A scalar value or 1D array (for 2D arrays use an image). This is probably the most complicated type.

dim_check is an integer that can be either positive, negative or 0. If it is 0, a scalar value is expected. If it is negative, any one-dimensional array is valid, and will be passed unchanged. Finally, if it is positive, it points to a parameter of type 'image', whose dimensionality determines the size for this array. For example, if dim_ckeck is 1, and parameter 1 is a 2D image, then this parameter is expected to have two elements (one for each dimension). A scalar will also be accepted (and extended by the automatic parameter parsing algorithm), but a 3-element array will not. The reason for this is that DIPlib expects some arrays to have one value per dimension in the input image.

range_check determines the valid range for the values in the array. It must be either an array with two values (minimum and maximum valid values), an empty array (meaning [-Inf Inf]), or one of a few strings that are defined for common ranges:

- Integer types: 'N+' = [1 Inf]. 'N-' = [-Inf -1]. 'N' = [0 Inf], 'Z' = [].
- Real types: 'R' = []. 'R+' = [0 Inf]. 'R-' = [-Inf 0].

Note that if you specify a range by two values, it is considered real. If you require some (finite) integer range, use the type 'option'.

default is any array that satisfies the requirements of dim_check and range_check. For positive dim_check, provide a scalar as default value, since it is always valid.

'measureid'

A measurement ID in a dip_measurement object.

dim_check is used as in 'array', except that it must be a positive integer. That is, it always points to a parameter of tye 'measurement' from which to get a measurement ID.

required should be 0, and dim_check and default are ignored. The default is always the first measurement in the dip_measurement object (passing the empty string yields the default as well).

'option'

A value (numerical or string) selected from a list. The GUI presents a drop-down list with options to choose from.

range_check is a cell array with possible options, for example:

- \bullet {1,2,3,4}
- {'rectangular', 'elliptic', 'parabolic'}

required should be 0. default is any one value from the list. dim_check is ignored.

'optionarray'

A cell array (with numbers or strings) selected from a list. The GUI presents an edit box with a button. Pressing the button brings up a dialog box that allows selecting one or more items from a list.

range_check is as in 'option'. required should be 0. default is a cell array with values from the list, or a single value. dim_check is ignored.

'cellarray'

A cell array (with arbitrary cell content). dim_check and range_check are ignored. default must be a cellarray.

'infile'

The name of an existing file (for input). The GUI presents an edit box and a button that, when pressed, presents an "Open as..." dialog box.

range_check is a string containing the mask for the filename, dim_check is ignored, and default is a string with the default file name.

'outfile'

The name of a file (for output). The GUI presents an edit box and a button that, when pressed, presents an "Save as..." dialog box. See the comments for 'infile'.

'indir'

The GUI presents an edit box and a button that, when pressed, presents an "Select a directory ..." dialog box. range_check and dim_check are ignored, default gives the default directory.

'handle'

The handle of a figure window. Only figure windows created by **dipshow** are considered. It is possible to enter a handle or the name of a variable (the figure to which it is linked is used). The GUI shows a drop-down list with the titles of all figure windows that fit the description.

range_check is a cell array with strings that specify the type of figure window required. All figure windows that satisfy any of the strings are valid. Examples are:

- {'1D', '2D', '3D'}: either two- or three-dimensional displays.
- {'Color', 'Grey', 'Binary'}: either color, grey-value or binary displays.
- {'1D_Color', '2D_Grey'}: either 1D color or 2D grey-value displays.

An empty array means that any window created by dipshow is acceptable. Note that these strings are not case-sensitive. It is, however, important that the order shown here is maintained. No window will satisfy the string 'Binary_2D', for example, but '2D_Binary' is valid.

dim_check and default are ignored. The default value is always gcf (the current figure).

'string'

Any string. dim_check and range_check are ignored. default must be a string.

'boolean'

The value 1 or 0. Also accepted are the strings 'yes', 'no', 'true' and 'false', as well as only the first character of each. The GUI presents a drop-down box with the words "yes" and "no". The automatic parameter parsing, however, always returns either 1 or 0. dim_check and range_check are ignored. default should be any of the accepted values.

```
% The next section handles all parameter parsing
try
   [var1,var2,var3] = getparams(paramlist,varargin{:});
catch
   if ~isempty(paramerror)
       error(paramerror)
   else
       error(firsterr)
   end
end
% Below, add your own code
image_out = process_image(var1,var2,var3);
```

Figure 7.3: Skeleton for a function that uses automatic parameter parsing.

7.12 Automatic Parameter Parsing

To use automatic parameter parsing (through the getparams function), you no longer (since version 1.4.1) need to copy files from the dipimage/private/ directory into your own private/ directory. The function getparams is directly available.

The code shown in Figure 7.3 needs to be inserted into your function (after the portion used for the GUI functionality). As you can see, the same data structure paramlist is used for automatic parameter parsing and for the GUI.

It is not necessary to use the function getparams. If you don't, you will have a more flexible parameter parsing, but if you do, you will need to write less code: parameters are guaranteed to be of the chosen types and in the chosen intervals.

Chapter 8

Customizing the DIP image Environment

8.1 Figure Windows

The single most important thing that can be customized in the DIP *image* environment is the way that images are displayed to figure windows. It is possible to link a variable name with a figure handle, such that that variable is always displayed in that same window. If a variable is not linked to any window, a new one will be opened to display it. The command dipfig is used to create these links (see Section 7.7).

8.2 Graphical user Interface

The DIP *image* toolbox contains a GUI with a menu system for easy calling of toolbox functions. It is not necessary to use this GUI, but it is the easy way of finding the functions defined in the toolbox (see Section 7.1).

All functions that appear on the menus are in the toolbox directory or on the DIP image path. If you want to add any functions to this menu system, read Section 7.11. If you want your function to appear in a specific place in the menu system, you will have to create a function called localdipmenus. It gives you the opportunity to edit the cell array menulist created by dipmenus, which specifies in which menu each function should be placed. It also allows you to provide a list of functions not to be put on the menus at all.

The cell array menulist has two columns. The left column gives the names of the menus, the right column contains cell arrays with the function names that are to be put under each menu. Any function not mentioned in this array will be put at the bottom of the menu specified by the function itself, in alphabetical order. See the code for dipmenus to see how it is defined.

The list of functions to be excluded overrides the menulist. Any function in this list will not be queried when generating the menu system.

Figure 8.1 provides an example for a localdipmenus function. It adds a menu to the menulist, and puts all AVI-related functions on the exclude list. Note the string 'sep' that inserts a separator in the menu.

An alternative is to edit the dipmenus function. We do not recommend this because you will be required to make the same changes each time you install a new version of DIP *image*.

The DIP image GUI will call the dipinit command when starting. It initializes the working environment. See Section 8.3.

Another thing that can be customized in the GUI is whether the command it executes should

```
function [menulist,excludelist] = localdipmenus(menulist)
I = size(menulist,1)+1;
menulist{I,1} = 'My Functions';
menulist{I,2} = {'gaussf','unif','kuwahara','sep','closing','opening'};
excludelist = {'readavi','writeavi','writedisplayavi'};
```

Figure 8.1: Sample localdipmenus function.

be printed to MATLAB's command window. This is useful for copying and pasting the command being executed to some script or function. It is on by default, and can be switched off by typing

```
dipsetpref('PutInCommandWindow','off')
```

8.3 Initialization File

The DIP image GUI will call the dipinit command when starting. It initializes the working environment, setting up figure windows and the like. You can also call it yourself, to return the windows to their starting positions. You can edit this file to suit your need (or you can create a local copy, making sure that it sits on the MATLAB path before the original one; this is recommended in multi-user systems). Since it is a script, not a function, it can initialize some variables if you like. It can also be used to position the DIP image GUI to the place of your liking:

```
set(0,'ShowHiddenHandles','on')
h = findobj('tag','DIPimage_Main_Window');
set(h,'Position',[500,600,500,100])
set(0,'ShowHiddenHandles','off')
```

8.4 Other Settings

Other settings are available through the dipsetpref command (see Section 7.8). They are listed below:

CommandFilePath

```
Value: string
Default: ','
```

This setting stores the path used by the DIP *image* GUI to find the functions that must be added to the menu system. The DIP *image* toolbox directory does not need to be in this path, since it is always used. On UNIX and Linux systems, directories are separated by a colon (:), on Windows systems by a semicolon (;).

ComplexMappingDisplay

Value: string
Default: 'x+iy'

This only affects display of complex images. While using Pixel testing to retrieve a pixel value in the Mapping: Magnitude or Mapping: Phase the value can be displayed as x+iy or as magnitude or phase. Possible values are r/phi and x+iy.

ComputationLimit

Value: integer
Default: 65536

This only affects operations done on dip_image objects in MATLAB (not operations that involve DIP lib itself). MATLAB can only compute using double-precision floating-point values, so images of any other type are converted to double to do the computation. This number sets the size of the blocks in which an image is chopped to do the computation (to avoid excessive memory usage).

CurrentImageFileDir

Value: string
Default: ','

This setting stores the directory last visited by the file selection dialog boxes of readim, readcolorim, readroim and writeim. It is used by these functions to open the file selection dialog box in the directory you last used.

DebugMode

Value: 'on' or 'off'

Default: 'off'

When this option is turned on, error messages are more verbose, and errors in the DIP *image* toolbox are easier to track. It is used for developing GUI functions.

DefaultActionState

Value: string

Default: 'diptest'

This is the action mode that will be enabled by dipshow when displaying an image to a new window, or to a window with a mode not compatible with the image being displayed. Possible values are 'none', 'diptest', 'diporien', 'dipzoom' and 'dipstep'. See Section 6.2.

DefaultColorMap

Value: string
Default: 'grey'

This is the colormap that will be used by dipshow when displaying an image to a new window. Possible values are 'grey', 'periodic' and 'labels'. See Sections 7.3 and 6.1.

DefaultComplexMapping

Value: string
Default: 'abs'

This is the complex mapping mode that will be enabled by dipshow when displaying an image to a new window, or to a window with a mode not compatible with the image being displayed. Possible values are 'abs', 'phase', 'real' and 'imag'. See Sections 7.3 and 6.1.

DefaultFigureHeight

Value: integer
Default: 256

This value determines the height of a window created by dipshow or dipfig, unless a size is explicitly given.

DefaultFigureWidth

Value: integer
Default: 256

This value determines the width of a window created by dipshow or dipfig, unless a size is explicitly given.

DefaultGlobalStretch

Value: 'on' or 'off'

Default: 'off'

Set this option if you want global stretching for 3D images on by default. See Sections 7.3 and 6.1.

DefaultMappingMode

Value: string
Default: 'normal'

This is the mapping mode that will be enabled by dipshow when displaying an image to a new window, or to a window with a mode not compatible with the image being displayed. Possible values are 'lin', 'percentile', 'log', 'base', 'angle' and 'orientation'. See Sections 7.3 and 6.1.

DefaultSlicing

Value: string
Default: 'xy'

Sets the direction in which 3D volumes are sliced by default. Possible values are 'xy', 'xz' and 'yz'. See Sections 7.3 and 6.1.

DerivativeFlavour

Value: string

Default: 'spatial'

Sets the way Gaussian derivatives are computed: either by spatial convolution with a Gaussian derivative or via the Fourier domain. The second is slower and uses more memory, but will be more accurate for small sigmas. Possible values are 'spatial' and 'fourier'.

DisplayToFigure

Value: 'on' or 'off'

Default: 'on'

When this setting is 'on', the display method of the dip_image object sends the image data to a figure window. When it is 'off', disp is called instead. The display method is called when a MATLAB command does not end with a semicolon. See Section 4.2 for more information on this behavior.

EnableKeyboard

Value: 'on' or 'off'

Default: 'on'

If you set this value to 'off', the keyboard will be disabled when displaying an image. This is useful for Windows machines, on which the figure window will get keyboard focus when displaying an image. This can be annoying when you want to continue typing. Enable the keyboard callback for a figure window using the appropriate menu item under "Actions".

FileWriteWarning

Value: 'on' or 'off'

Default: 'off'

If you set this to on everything you write a non-standard TIFF image in terms of byte depth or compression a warning will be displayed on the screen. This is useful as many image viewer cannot read anything but uint8 uncompressed images (e.g. the standard Windows image TIFF viewer).

Gamma

Value: 3x1 array of floats

Default: [1 1 1]

These parameters control the display of all colour images shown by dipshow. If the values are different from unity a gamma correction is applied before displaying any image. The different values control the behaviour for the Red, Green and Blue channel respectively.

GammaGrey

Value: float
Default: 1

Similar to Gamma, but only for grey-value images. This parameter controls the display of all

grey-value images shown by dipshow. If the value is different from unity a gamma correction is applied before displaying any image.

ImageFilePath

Value: string
Default: ','

This setting stores the path used to find image files. The functions readim, readcolorim and readroim look for a file first in the current directory, and then in each of the directories given by this option, unless the filename already contains a path. On UNIX and Linux systems, directories are separated by a colon (:), on Windows systems by a semicolon (;).

ImageSizeLimit

Value: integer Default: 2048

This is the maximum size of an image automatically displayed through display. If any of the sizes of an image is larger, you will need to display it manually using dipshow. The reason behind this behavior is that such an image is most likely to be created accidentally, and not meant for display anyway. For example, a(a>10) returns a 1D image with all pixel values of a larger than 10; this is very useful, but not interesting to look at. For a large a (such as a 3D image), the display of the resulting 1D image might require a lot of memory.

MorphologicalFlavour

Value: integer
Default: 0

This setting stores the state usually set though dip_morph_flavour. The value 0 causes the morphological operations to follow the definition of Serra and Soille, 2 is for the definition followed by Heijmans and Haralick. Any other value is equivalent to 0.

PutInCommandWindow

Value: 'on' or 'off'

Default: 'on'

This option causes commands that are executed from the DIP *image* GUI to be printed to the command window. This makes it possible to copy and paste commands being executed to a MATLAB script.

TrueSize

Value: 'on' or 'off'

Default: 'on'

This setting controls whether diptruesize is called after an image is displayed to a figure window (see Section 7.4).

BoundaryCondition

Value: string

Default: 'symmetric'

Setting this value causes dip_setboundary to be called. This causes the algorithm that extends the image beyond its boundary to change, for all filter operations.

Note that calling dip_setboundary does change this setting, although it will not be reported correctly by dipgetpref.

Truncation

Value: integer

Default: 3

Setting this value causes dip_settruncation to be called. This causes all versions of the Gaussian filter to change (this number represents the extent of the filtering kernel, in terms of the given parameter sigma).

Note that calling dip_settruncation does change this setting, although it will not be reported correctly by dipgetpref.

Chapter 9

Low-level DIPlib Interface

The DIP *image* toolbox is build around DIP *lib*, which is a library of image-processing functions written in C. Most of these functions can be directly called from within MATLAB through a low-level interface. This interface is not as easy to use as the toolbox functions, but it is more complete.

9.1 The Setup

For each function available in the low-level interface, there is a MEX-file (which is just a shared object MATLAB links to), and an M-file, which just contains some help on calling the function. However, this help is very meager, since it only lists the name and type of each parameter. Only when the function does more than just call the equivalent DIP lib function, are there any comments on how the function works. You will need to check the online DIP lib documentation to see what each of the parameters does. The online function reference can be found at:

http://www.qi.tnw.tudelft.nl/DIPlib/docs/reference/.

9.2 Calling DIPlib Functions

You will notice that the parameters required by the interface are exactly those required by the C functions, but with some exceptions:

- The output parameters are naturally placed at the left-hand side of the function call. In the corresponding C functions, they are always on the right-hand side. The interface generates an error when the C function returns an error code.
- The parameters corresponding to the random number generator are stored internally by the interface and thus are not needed at the command line.
- The parameters corresponding to the extension of the image beyond the boundaries and the truncation of the Gaussian kernel are also not present in the interface. The default values for these parameters are used. These defaults can be set and read with the functions dip_setboundary, dip_getboundary, dip_settruncation and dip_gettruncation.
- None of the DIP lib library variables is passed back to MATLAB. This means that any parameter of the type dip_Resources and the like are not present in the MATLAB interface.
- Enumerated values in the C functions have been implemented as strings in the MATLAB interface. The function's help will list these strings, which are easy to map to the names

of the enumerated values (use help parameters if in doubt). If a function requires an array of these values, the strings should be put in a cell array.

By the way, all DIP *lib* interface functions have all characters in lower-case, and start with the characters "dip_", or "dipio_" for the functions in the dipIO extension library.

Whenever an image is required as input, it is legal to pass either a numeric MATLAB array or a dip_image object. Parameters of the type dip_FloatArray and the like are usually expected to be of the same length as the dimensionality of the input image. The low-level interface is so low-level that it does not even check these simple things, and DIP lib will generate an error if the array is not of the correct size. Many parameters are allowed to be null pointers in the C library. Sometimes it is possible to pass an empty array as such a value (for example, pass an empty array as a mask image if no masking is required).

9.3 Example Function Call

As an example, let us call the DIP *lib* functiondip_Gauss from within MATLAB. The declaration of the C function is:

```
dip_Error dip_Gauss (
   dip_Image in,
   dip_Image out,
   dip_BoundaryArray boundary,
   dip_BooleanArray process,
   dip_FloatArray sigmas,
   dip_IntegerArray parOrder,
   dip_float truncation
);
```

As explained earlier, the parameters boundary and truncation should not be used from within MATLAB. The globally defined default values will be used. The parameter out should be on the left of the function call. What remains is this:

```
out = dip_gauss(in,process,sigmas,parOrder);
which we can verify by typing
help dip_gauss
```

This also gives us the expected data types for each parameter. The data types correspond

Parameter in can be a dip_image or any numeric array. The length of the other arrays should match the dimensionality of the image. We will use a two-dimensional image a, which we want to smooth by convolution with a Gaussian with sigma 5 in the y-direction and 2 in the x-direction. We would write

```
b = dip_gauss(a,[1,1],[2,5],[0,0]);
```

As can be read in the online help for DIP lib, parOrder indicates the order of the derivative. The process array, which is present in many DIP lib functions, can be used to apply the filter only in some dimensions.

The dipimage/demos/ directory contains some example M-files. Examine demogdt.m for an example on using the low-level interface.